

TI-Nspire™ and TI-Nspire™ CAS Computer Software Upgrade Instructions


[Determining your Computer Software version](#)

[Uninstalling a previous version](#)

[What if I have previous version of the Computer Software, but I have not activated it yet?](#)


If you already have a previous version of TI-Nspire™ or TI-Nspire CAS software installed on your computer, you will need to **uninstall your current version** before you can install the latest version.

If you are trying to install the current version of the Computer Software and a previous version is detected, you will be prompted to uninstall any existing versions in order to continue.




Determining your Computer Software version

If you are unsure which version of the TI-Nspire™ Computer Software is installed on your computer, click **Help > About** to view the version:




Uninstalling a previous version


1. To access your Add/Remove Programs menu, you must first open the Control Panel. To do so, go to **Start > Settings > Control Panel**.




2. Once the Control Panel is open, select the Add/Remove Programs option.




3. Scroll down to the TI-Nspire or TI-Nspire CAS Computer Software item and click **Remove**.



4. When prompted, click **“Yes”** to confirm that you wish to remove the previous version of TI-Nspire Computer Software from your computer.



5. Your system will update you when the removal has been completed. Once complete, you are now ready to begin to install the latest version of the TI-Nspire or TI-Nspire CAS Computer Software.



6. Insert your Computer Software CD or click on the downloaded .exe file to install the Computer Software. For detailed instructions, please refer to the TI-Nspire™ Computer Software Installation Guide.

What if I have previous version of the Computer Software, but I have not activated it yet?

If you have a previous version of the TI-Nspire Computer Software on your computer that has not yet been activated (still in Trial mode), your license and serial number will not be valid for the latest installation.

1. Use your license and serial numbers to activate the previous version that is currently running in trial mode on your computer.
 - a. If you have not yet installed the previous version but have purchased it, please **install and activate**, then proceed to step 2.
 - b. For detailed instructions on how to install, please refer to the TI-Nspire™ Computer Software Installation Guide.
2. Follow the Uninstall instructions listed above to remove the current version.
3. Start a new install for the current version. The program will recognize your previous activation. For detailed instructions on how to install, please refer to the TI-Nspire™ Computer Software Installation Guide.